



AV CaptureAll

How-to Guide: Transfer AVC Settings to a New PC

AV Capture All
19125 Northcreek Parkway, STE 120
Bothell, WA 98011
Phone: 888.360.2822
support@avcaptureall.com
<http://www.avcaptureall.net/>

Overview

The purpose of this guide is to walk you through the steps necessary for transferring AVC settings to a new PC. If at any time you have questions regarding this process, please call our customer support line at [888-360-2822](tel:888-360-2822) or email us at Support@AVCaptureAll.com.

Directions

Step 1: Locate AVC Settings on the Old PC

1. On the PC where AVC is already set up, navigate to the following folder:
C:\ProgramData\AV Capture All\Settings\AVAVA (or AVJRA for Judicial customers)
2. Locate the file named AppConfig.xml. This file contains the main settings.
3. (Optional) If you have modified any of the following files, you may also want to copy them:
 - o Attendees.xml
 - o AttendeeTitles.xml
 - o AddinShortcutKeys.xml


Note: The settings are stored in the ProgramData location only for the Windows login that installed AVC. If you are copying settings for a different Windows login, locate the settings here instead:

C:\Users\[USERNAME]\AppData\Local\AV Capture All\Settings\AVAVA

Step 2: Transfer the Settings to the New PC

1. Copy the **AppConfig.xml** file (and any additional files) to an external drive or a cloud storage service.
2. Navigate to the same folder location on the new PC:
C:\ProgramData\AV Capture All\Settings\AVAVA
 - o If using a different Windows login than the one that installed AVC, use:
C:\Users\[USERNAME]\AppData\Local\AV Capture All\Settings\AVAVA

Note: If you're unsure whether this Windows login was used to install AVC and want to verify the settings location, open the Registry Editor and navigate to Computer\HKEY_CURRENT_USER\Software\AV Capture All\Settings and check the Data from the AVAVA key.



3. Paste the copied files into the respective folder.

Step 3: Verify the Settings

1. Launch AVC on the new PC.
2. Confirm that your settings have been successfully applied.
3. If necessary, run AVC once before copying the files to ensure the correct folder structure is created.

Summary

By following the steps above, you can efficiently transfer AVC settings without needing to configure them manually. If you encounter any issues, please call our customer support line at [888-360-2822](tel:888-360-2822) or email us at Support@AVCaptureAll.com.